



MRBEER[®]



Midnight Lantern Pumpkin Stout Brewing Instructions

What You Get

- 1 Can Coopers Dark Unhopped Malt Extract
- 1 Packet BrewMax DME Smooth
- 1 Packet Lactose
- 1 Packet Chocolate Malt
- 1 Packet Crystal 40 Malt
- 1 Packet Carapils Malt
- 1 Packet Glacier Hops
- 1 Packet S-33 Yeast
- 2 Muslin Hop Sacks
- 1 Packet No-Rinse Cleanser

You Provide

- 12–15 oz Pumpkin Puree, lightly browned in a pan
- 1/2 Tablespoon Pumpkin Pie Spice
- 1 Tablespoon Vanilla Extract

Step 1: Sanitize

Cleaning and sanitizing are some of the most important steps in brewing. Make sure anything that touches your beer is properly sanitized before use.

1. Fill the fermenter with warm water to line 1.
2. Add 1/2 packet of No-Rinse Cleanser and stir until dissolved.
3. Save the remaining 1/2 packet of cleanser for bottling.
4. Swirl the sanitizer to coat the inside of the fermenter and lid.
5. Open the spigot and let sanitizer flow for 5 seconds, then close.





MRBEER®



6. Pour the remaining sanitizer into a large bowl.
 7. Soak your spoon, whisk, can opener, measuring cup, hop sacks, and anything else that will touch your beer in the sanitizer for at least 2 minutes.
 8. Do not rinse or dry sanitized equipment.
-

Step 2: Prepare the Grains, Hops, and Pumpkin

1. Add the Chocolate Malt, Crystal 40 Malt, and Carapils Malt to one muslin hop sack.
 2. Tie the grain sack closed loosely so the grains can move freely inside the sack.
 3. Add the Glacier hops to the second muslin hop sack.
 4. Tie the hop sack closed loosely so the hops have room to expand.
 5. Add 12–15 oz of pumpkin puree to a small saucepan.
 6. Lightly brown the pumpkin puree over medium heat, stirring often.
 7. Stir in 1/2 tablespoon pumpkin pie spice.
 8. Remove the pumpkin mixture from heat and set it aside.
-

Step 3: Steep the Grains

1. Add 8 cups of water to a 1-gallon or larger boil pot.
 2. Heat the water to 155–160°F.
 3. Add the grain sack to the pot.
 4. Steep the grains for 30 minutes, maintaining 155–160°F.
 5. After 30 minutes, turn off the heat and remove the grain sack.
 6. Place the grain sack in a colander over the pot.
 7. Rinse the grain sack with 1 cup of hot water around 160°F, allowing the runoff to drain back into the pot.
 8. Do not squeeze the grain sack.
 9. Discard the used grain sack.
-

Step 4: Add Smooth DME



3366 N. Dodge Blvd. Tucson, AZ 85716

mrbeer.com





1. Increase the heat to medium-high.
 2. Slowly sprinkle in the BrewMax DME Smooth while stirring.
 3. Continue stirring until the dry malt is dissolved.
 4. Keep stirring as the mixture heats to help control foam.
 5. If foam begins to rise too high, briefly remove the pot from heat and lower the temperature slightly.
 6. Continue heating and stirring until the foam settles and the mixture reaches a low rolling boil.
-

Step 5: Boil the Glacier Hops, Pumpkin, and Lactose

1. Add the Glacier hop sack to the boiling DME mixture.
 2. Boil for 25 minutes.
 3. Add the lactose and spiced pumpkin puree.
 4. Stir to combine.
 5. Boil for 5 more minutes, for 30 minutes total.
 6. After 30 minutes total, remove the pot from heat.
-

Step 6: Add the Dark UME

1. Open the Coopers Dark Unhopped Malt Extract.
 2. Add the Dark UME to the hot mixture.
 3. Stir until thoroughly mixed.
 4. This mixture is called wort.
-

Step 7: Fill the Fermenter

1. Fill the fermenter with cold tap water to line 1.
2. Pour the wort into the fermenter.
3. Top off with cold water to line 2, or to 8.5 liters if using another fermenter.
4. Stir the wort vigorously with a sanitized spoon or whisk.





MRBEER®



Step 8: Add Yeast and Ferment

1. Sprinkle the S-33 Yeast into the fermenter.
2. Do not stir after adding yeast.
3. Screw on the lid.
4. Place the fermenter out of direct sunlight in a location with a consistent temperature between 68°F and 72°F.
5. Ferment for 21 days total.

Step 9: Add Vanilla on Day 7

On day 7 of fermentation, add the vanilla extract.

1. Sanitize anything that will touch the vanilla addition.
2. Carefully open the fermenter.
3. Add 1 tablespoon vanilla extract.
4. Close the fermenter right away.
5. Allow the beer to ferment for 14 more days, for 21 days total.

Step 10: Bottle and Carbonate

After 21 days total, taste a small sample. If it tastes like flat beer, it is ready to bottle. If it tastes sweet, let it ferment for 3 more days. Do not leave the beer in the fermenter longer than 24 days total.

1. Fill a 1-gallon container with warm water.
2. Add the remaining 1/2 packet of No-Rinse Cleanser and stir until dissolved.
3. Distribute the sanitizer equally among your bottles.
4. Cap the bottles and shake vigorously.
5. Let bottles sit for 10 minutes, then shake again.
6. Empty the sanitizer into a large bowl and use it to sanitize any other bottling equipment.
7. Do not rinse.
8. Add 2 carbonation drops to each 740 mL bottle.





MR BEER[®]



9. Fill each bottle at an angle, leaving about 2 inches of headspace.
 10. Cap bottles tightly.
 11. Gently turn each bottle over to check the seal.
 12. Store bottles upright and out of direct sunlight at 70°F to 76°F.
 13. Carbonate for at least 14 days. Cooler temperatures may require an additional week.
 14. For best flavor, condition this pumpkin stout for another week or two after carbonation.
-

Step 11: Enjoy

1. After carbonation and conditioning, chill one bottle for 48 hours.
2. Pour slowly into a glass, leaving the sediment behind in the bottle.
3. Take a sip and enjoy it. You just crushed this recipe.
4. If the beer still tastes young, leave the remaining bottles at room temperature for another week or two, then try again.

